### LewanSoul Bus Servo Communication Protocol


### 1.Summary

Using asynchronous serial bus communication method, theoretically, up to 253 robot servos can be connected into chain through the bus, you can unify control them through the UART asynchronous serial interfaces. Each servo can be set to a different node address, multiple servos can be unified or controlled independently. Communicating with the user's host computer software(controller or PC) through the asynchronous serial interface, you can set its parameters, function control. Sending instructions to servo through the asynchronous serial interface, the servo can be set to the motor control mode or position control mode. In the motor control mode, servo can be used as a DC reduction motor with adjustable speed; In the position control mode, servo has 0-240 degrees of rotation range with Plus  $\pm$  30 ° deviation adjustable range, in this range with precise position control performance, speed adjustable.

Half-duplex UART asynchronous serial interface which conforms to the protocol can communicate with the servo and control servo in different ways.

#### 2.UART Interface schematic diagram

Servo uses the program code to perform the timing control to the UART asynchronous serial interface, realizes the half-work asynchronous serial bus communication, the communication baud rate is 115200bps, and the interface is simple, the protocol is simplified. In your own designed controller, the UART interface for communication with the servo must be handled as shown below.



#### **3.Command Packet**

Command packet format

Table 1:

Header	ID number	Data Length	Command	Parameter	Checksum
0x55 0x55	ID	Length	Cmd	Prm 1 Prm N	Checksum

Header: Two consecutive 0x55 are received indicating the arrival of data packets.

ID: Each servo has an ID number. ID number ranges from  $0 \sim 253$ , converted to hexadecimal  $0x00 \sim 0xFD$ .

Broadcast ID: ID No. 254 (0xFE) is the broadcast ID. If the ID number issued by the controller is 254 (0xFE), all servos will receive instructions, but they all do not return the response message, (except for reading the servo ID number, Please refer to the following instructions for detailed instructions) to prevent bus conflict.

Length(data): Equal to the length of the data that is to be sent (including its own one byte). That is, the length of the data plus 3 is equal to the length of this command packet, from the header to the checksum.

Command: Control the various instructions of servo, such as position, speed control.

Parameter: In addition to commands, parameter are control informations that need to add.

Checksum: The calculation method is as follows:

Checksum=~(ID+ Length+Cmd+ Prm1+...PrmN)If the numbers in the brackets are calculated and exceeded 255,Then take the lowest one byte, "~" means Negation.

#### 4.Command type

There are two kinds of commands, write command and read command. Write command: normally, it followed by parameters, write the parameters of the corresponding function into the servo to complete a certain action. Read command: normally, it will not followed by parameters, when the servo received "read command", it will return the corresponding data immediately, the returned command value with parameters is the same as the "read command" value that sent to the servo. So the PC software must immediately prepare to change itself to "read condition" after it sends the reading command.

The following table is command that the PC software send to servos.

Command name	Command value	Length
SERVO_MOVE_TIME_WRITE	1	7
SERVO_MOVE_TIME_READ	2	3
SERVO_MOVE_TIME_WAIT_WRITE	7	7
SERVO_MOVE_TIME_WAIT_READ	8	3
SERVO_MOVE_START	11	3
SERVO_MOVE_STOP	12	3
SERVO_ID_WRITE	13	4
SERVO_ID_READ	14	3
SERVO_ANGLE_OFFSET_ADJUST	17	4
SERVO_ANGLE_OFFSET_WRITE	18	3
SERVO_ANGLE_OFFSET_READ	19	3
SERVO_ANGLE_LIMIT_WRITE	20	7
SERVO_ANGLE_LIMIT_READ	21	3
SERVO_VIN_LIMIT_WRITE	22	7
SERVO_VIN_LIMIT_READ	23	3
SERVO_TEMP_MAX_LIMIT_WRITE	24	4
SERVO_TEMP_MAX_LIMIT_READ	25	3
SERVO_TEMP_READ	26	3
SERVO_VIN_READ	27	3
SERVO_POS_READ	28	3
SERVO_OR_MOTOR_MODE_WRITE	29	7
SERVO_OR_MOTOR_MODE_READ	30	3
SERVO_LOAD_OR_UNLOAD_WRITE	31	4
SERVO_LOAD_OR_UNLOAD_READ	32	3
SERVO_LED_CTRL_WRITE	33	4
SERVO_LED_CTRL_READ	34	3
SERVO_LED_ERROR_WRITE	35	4
SERVO_LED_ERROR_READ	36	3

Command name: Just for easy identification, the user can also set according to their own habits. Command name suffix "\_WRITE" which represents write command, and the suffix "\_READ" represents read command.

Command value: That is, the command Cmd in command packet of Table 1

Length: that is the length(data length) in table 1

Parameter 1: lower 8 bits of angle value

Parameter 2: higher 8 bits of angle value.range  $0\sim100$ . corresponding to the servo angle of  $0\sim240$ °, that means the minimum angle of the servo can be varied is 0.24 degree.

Parameter 3: lower 8 bits of time value

Parameter 4: higher 8 bits of time value. the range of time is 0~30000ms. When the command is sent to servo, the servo will be rotated from current angle to parameter angle at uniform speed within parameter time. After the command reaches servo, servo will rotate immediately.

Read the angle and time value which sent by SERVO\_MOVE\_TIME\_WRITE to the servo

For the details of the command packet that the servo returns to host computer, please refer to the description of Table 4 below.

3. Command name: SERVO\_MOVE\_TIME\_WAIT\_WRITE

Command value: 7 Length: 7

Parameter1: lower 8 bits of preset angle

Parameter2: higher 8 bits of preset angle. range  $0\sim100$ . corresponding to the servo angle of  $0\sim240$ °. that means the minimum angle of the servo can be varied is 0.24 degree.

Parameter3: lower 8 bits of preset time

Parameter3: higher 8 bits of preset time. the range of time is 0~30000ms.

The function of this command is similar to this

"SERVO\_MOVE\_TIME\_WRITE" command in the first point. But the difference is that the servo will not immediately turn when the command arrives at the servo, the servo will be rotated from current angle to parameter angle at unifor m speed within parameter time until the command name SERVO\_MOVE\_ST ART sent to servo(command value of 11)

, then the servo will be rotated from current angle to setting angle at uniform speed within setting time

4. Command name: SERVO MOVE TIME WAIT READ

Command value: 8 Length: 3

Read the preset angle and preset time value which sent by

SERVO MOVE TIME WAIT WRITE to the servo

For the details of the command packet that the servo returns to host computer, please refer to the description of Table 3 below.

5. Command name: SERVO\_MOVE\_START Command value: 11 Length: 3

With the use of command SERVO\_MOVE\_TIME\_WAIT\_WRITE, described in point 3

Command name: SERVO\_MOVE\_STOP Command value: 12 Length: 3

When the command arrives at the servo, it will stop running immediately if the servo is rotating, and stop at the current angle position.

- 7. Command name: SERVO\_ID\_WRITE Command value: 13 Length: 4 Parameter 1: The servo ID, range 0 ~ 253, defaults to 1. The command will re-write the ID value to the servo and save it even when power-down.
- 8. Command name: SERVO\_ID\_READ Command value: 14 Length: 3 Read servo ID, For the details of the command package that the servo returns to host computer, please refer to the description of Table 4 below.
- Command name: SERVO\_ANGLE\_OFFSET\_ADJUST Command value: 17 Length: 4

Parameter 1: servo deviation, range -125 $\sim$  125, The corresponding angle of -30  $^{\circ}$   $\sim$  30  $^{\circ}$ , when this command reach to the servo, the servo will immediately rotate to adjust the deviation.

Note 1:The adjusted deviation value is not saved when power-down by this command, if you want to save please refer to point 10.

Note 2: Because the parameter is "signed char" type of data, and the command packets to be sent are "unsigned char" type of data, so before sending, parameters are forcibly converted to "unsigned char" data and then put them in command packet.

Command name: SERVO\_ANGLE\_OFFSET\_WRITE
Command value: 18 Length: 3

Save the deviation value, and support "power-down save". The adjustment of the deviation is stated in point 9

11. Command name: SERVO\_ANGLE\_OFFSET\_READ Command value: 9 Length: 7

Read the deviation value set by the servo,

For the details of the command packet that the servo returns to host computer, please refer to the description of Table 4 below.

Parameter 1: lower 8 bits of minimum angle

Parameter 2: higher 8 bits of minimum angle, range 0~1000

Parameter 3: lower 8 bits of maximum angle

Parameter 4: higher 8 bits of maximum angle, range 0~1000

And the minimum angle value should always be less than the maximum angle value. The command is sent to the servo, and the rotation angle of the servo will be limited between the minimum and maximum angle. And the angle limit value supports 'power-down save'.

# 13. Command name: SERVO\_ANGLE\_LIMIT\_READ Command value: 21 Length: 3

Read the angle limit value of the servo, for the details of the instruction packet that the servo returns to host computer, please refer to the description of Table 4 below.

### Command name: SERVO\_VIN\_LIMIT\_WRITE Command value: 22 Length: 7

Parameter 1: lower 8 bits of minimum input voltage

Parameter 2: higher 8 bits of minimum input voltage, range 4500~12000mv

Parameter 3: lower 8 bits of maximum input voltage

Parameter 4: higher 8 bits of maximum input voltage, range 4500~12000mv And the minimum input voltage should always be less than the maximum input voltage. The command is sent to the servo, and the input voltage of the servo will be limited between the minimum and the maximum. If the servo is out of range, the led will flash and alarm (if an LED alarm is set). In order to protect the servo, the motor will be in the unloaded power situation, and the servo will not output torque and the input limited voltage value supports for power-down save.

# 15. Command name: SERVO\_VIN\_LIMIT\_READ Command value: 23 Length: 3

Read the angle limit value of the servo, for the details of the instruction packet that the servo returns to host computer, please refer to the description of Table 4 below.

# Command name: SERVO\_TEMP\_MAX\_LIMIT\_WRITE Command value: 24 Length: 4

Parameter 1: The maximum temperature limit inside the servo range 50~100°C, the default value is 85°C, if the internal temperature of the servo exceeds this value the led will flash and alarm (if an LED alarm is set). In order to protect the servo, the motor will be in the unloaded power situation, and the servo will not output torque until the temperature below this value of the servo, then it will once again enter the working state.and this value supports for power-down save.

### 17. Command name: SERVO\_TEMP\_MAX\_LIMIT\_READ

Command value: 25 Length: 3

Read the maximum temperature limit value inside the servo, for the details of the command package that the servo returns to host computer, please refer to the description of Table 4 below.

### Command name: SERVO\_TEMP\_READ Command value: 26 Length: 3

Read the Real-time temperature inside the servo, for the details of the instruction packet that the servo returns to host computer, please refer to the description of Table 4 below.

### Command name: SERVO\_VIN\_READ Command value: 27 Length: 3

Read the current input voltage inside the servo, for the details of the instruction packet that the servo returns to host computer, please refer to the description of Table 4 below.

# 20. Command name: SERVO\_POS\_READ Command value: 28 Length: 3

Read the current angle value of the servo, for the details of the instruction packet that the servo returns to host computer, please refer to the description of Table 4 below.

### 21. Command name: SERVO\_OR\_MOTOR\_MODE\_WRITE

Command value: 29 Length: 7

Parameter 1: Servo mode, range 0 or 1, 0 for position control mode, 1 for motor control mode, default 0,

Parameter 2: null value

Parameter 3: lower 8 bits of rotation speed value

Parameter 4: higher 8 bits of rotation speed value. range -1000~1000,

Only in the motor control mode is valid, control the motor speed, the value of the negative value represents the reverse, positive value represents the forward rotation. Write mode and speed do not support power-down save.

Note: Since the rotation speed is the "signed short int" type of data, it is forced to convert the data to "unsigned short int "type of data before sending the command packet.

#### 22. Command name: SERVO OR MOTOR MODE READ

Command value: 30 Length: 3

Read the relative values of the servo, for the details of the command package that the servo returns to host computer, please refer to the description of Table 4 below.

## 23. Command name: SERVO\_LOAD\_OR\_UNLOAD\_WRITE Command value: 31 Length: 4

Parameter 1: Whether the internal motor of the servo is unloaded power-down or not, the range 0 or 1, 0 represents the unloading power down, and the servo has no torque output. 1 represents the loaded motor, then the servo has a torque output, the default value is 0.

# 24. Command name: SERVO\_LOAD\_OR\_UNLOAD\_READ Command value: 32 Length: 3

Read the state of the internal motor of the servo. for the details of the command package that the servo returns to host computer, please refer to the description of Table 4 below.

#### 

Parameter 1: LED light/off state, the range 0 or 1, 0 represents that the LED is always on. 1 represents the LED off, the default 0, and support power-down save

# 26. Command name: SERVO\_LED\_CTRL\_READ Command value: 34 Length3

Read the state of the LED light. For the details of the command packet that the servo returns to host computer, please refer to the description of Table 4 below.

#### 

Parameter 1: what faults will cause LED flashing alarm value, range 0~7 There are three types of faults that cause the LED to flash and alarm, regardless of whether the LED is in or off. The first fault is that internal temperature of the servo exceeds the maximum temperature limit (this value is set at point 16). The second fault is that the servo input voltage exceeds the limit value (this value is set at 14 points). The third one is when locked-rotor occurred.

. This value corresponds to the fault alarm relationship as shown below:

0	No alarm
1	Over temperature
2	Over voltage
3	Over temperature and
	over voltage
4	Locked-rotor
5	Over temperature and
	stalled
6	Over voltage and stalled

7 Over temperature, over voltage and stalled

# 28. Command name: SERVO\_LED\_ERROR\_READ command value: 36 Length: 3

Read the servo fault alarm value. For the details of the command packet that the servo returns to host computer, please refer to the description of Table 4 below.

#### Table4

Command name	Command value	length
SERVO_MOVE_TIME_READ	2	7
SERVO_MOVE_TIME_WAIT_READ	8	7
SERVO_ID_READ	14	4
SERVO_ANGLE_OFFSET_READ	19	4
SERVO_ANGLE_LIMIT_READ	21	7
SERVO_VIN_LIMIT_READ	23	7
SERVO_TEMP_MAX_LIMIT_READ	25	4
SERVO_TEMP_READ	26	4
SERVO_VIN_READ	27	5
SERVO_POS_READ	28	5
SERVO_OR_MOTOR_MODE_READ	30	7
SERVO_LOAD_OR_UNLOAD_READ	32	4
SERVO_LED_CTRL_READ	34	4
SERVO_LED_ERROR_READ	36	4

Table 4 is the command that servo return to the host computer, these commands will only return when host computer send a read command to servo, what's more, the returned command value is consistent with the read command that the host computer sent to servo. the difference is that the returned value has parameters. The format of the returned data command packet is the same as the command package that the host computer sent to servo, as in Table 1.

1.Command name: SERVO\_MOVE\_TIME\_READ Command value: 2

Length: 7

Parameter 1: lower 8 bits of angle value

Parameter 2: higher 8 bits of angle, range 0~1000

Parameter 3: lower 8 bits of time value

Parameter 4: higher 8 bits of time value, range 0~30000ms

2. Command name: SERVO\_MOVE\_TIME\_READ Command value: 8

Length: 7

Parameter 1: lower 8 bits of preset angle value

Parameter 2: higher 8 bits of preset angle, range 0~1000

Parameter 3: lower 8 bits of preset time value

Parameter 4: higher 8 bits of preset time value, range 0~30000ms

3. Command name: SERVO\_ID\_READ Command value: 14 Length: 4

Parameter 1: servo ID value, default value is 1

Description: ID read is a little bit special compared with other read commands, if the command packet ID is broadcast ID:254 (0xFE), the servo will return the response information, and other read commands will not return the response message when ID is broadcast ID. The purpose of this design is to inquiry the servo ID number via broadcast ID without knowing the ID number of the servo, but the limit is that the bus can only access a servo, or it will return data caused bus conflict.

4.Command name: SERVO\_ANGLE\_OFFSET\_READ Command value: 19 Length: 4

Parameter 1: The deviation set by the servo, range-125~125, default value is 0

5.Command name: SERVO\_ANGLE\_LIMIT\_READ Command value: 21 Length: 7

Parameter 1: lower 8 bits of minimum angle value

Parameter 2: higher 8 bits of minimum angle, range 0~1000

Parameter 3: lower 8 bits of maximum angle value

Parameter 4: higher 8 bits of maximum angle value, range 0~1000,The default value is 0, the maximum angle is 1000

6.Command name: SERVO\_VIN\_LIMIT\_READ Command value: 23 Length: 7

Parameter 1: lower 8 bits of input voltage value

Parameter 2: higher 8 bits of input voltage value ,range 6500~10000mv

Parameter 3: lower 8 bits of maximum input voltage value

Parameter 4: higher 8 bits of maximum input voltage value, range

6500~12000mv, The default value is 6500v, the maximum voltage is 12000

7.Command name: SERVO\_TEMP\_MAX\_LIMIT\_READ Command value: 25 Length: 4

Parameter 1: The maximum temperature limit inside the servo, range 50~100°C, default value is 85°C

8.Command name: SERVO\_TEMP\_READ Command value: 26 Length: 4

Parameter 1: The current temperature inside the servo, no default value

9.Command name: SERVO\_VIN\_READ Command value: 27

Length: 5

Parameter 1: lower 8 bits of current input voltage value

Parameter 2: higher 8 bits of current input voltage value, no default

10.Command name SERVO\_POS\_READ Command value: 28 Length: 5

Parameter 1: lower 8 bits of current servo position value

Parameter 2: higher 8 bits of current servo position value, no default

Description: Returned the angular position value need to be converted to the "signed short int" type of data, because the read angle may be negative

11.Command name: SERVO\_OR\_MOTOR\_MODE\_READ Command value: 30 Length: 7

Parameter 1: The current mode of the servo, 0 for the position control mode, 1 for the motor control mode, the default 0

Parameter 2: Null, set to 0

Parameter 3: lower 8 bits of rotation speed value

Parameter 4: higher 8 bits of rotation speed value ,range-1000~1000,Only valid in the motor control mode , control the motor speed, the negative value represents the reverse, positive value represents the forward

12.Command name: SERVO\_LOAD\_OR\_UNLOAD\_READ Command value: 32 Length: 4

Parameter 1: Whether the internal motor of the servo is unloaded power-down or not, range 0 or 1, 0 represents the unloading power down, and now servo has no torque output. 1 represents the loaded motor, then the servo has a torque output, the default value of 0.

13.Command name: SERVO\_LED\_CTRL\_READ Command value: 34 Length: 4

Parameter 1: LED light /off state, the range 0 or 1, 0 represents that the LED is always on. 1 represents LED is always off, the default 0.

14.Command name: SERVO\_LED\_ERROR\_READ Command value: 36 Length: 4

Parameter 1: What faults in the servo cause LED flash and alarm, range 0~7. The corresponding relation between the numerical value and the fault is shown in table 3.